

Quick overview of functions and features for Kiosk Mode, which is a full screen, automatic, single-user style of Player. *Feature available in Player 6.5+; refer to "Using Kiosk Mode" for instructions on operating Kiosk Mode*

Set up and activate Kiosk Mode


Step 1: Access Kiosk Settings

- A. Go to Admin Settings
- B. Go to Kiosk Settings; enter password, if prompted




Step 2: Kiosk Mode Setup

- A. Check the box next to **Enable Kiosk Mode**
- B. Choose Settings; see next for the Kiosk Mode settings available for Facilitator, Automatic Logout, and Playlist options
- C. Select on **OK** to save settings and restart Player in Kiosk Mode



Step 3: Turn Off Kiosk Mode

- A. To deactivate Kiosk Mode, select the **Admin Login** button
- B. Enter your password
- C. Player will restart in Full Mode



Manage Kiosk Mode options in Administrative Settings. These are the current available settings for Kiosk Mode in Player 6.5 and above.

Enable Kiosk Mode

Select this option to train a single User. Kiosk Mode replaces Mouse Mode in most instances, and can be run with or without a Facilitator.

- Select to enable Kiosk Mode
 - Requires a restart of Player

Kiosk Facilitator

Select this option to identify the facilitator responsible for setting up the session.

- Must identify Facilitator immediately
- Sets the Facilitator for all kiosk training until changed
- Data collected for Reporting

Repeat 'In Progress'

Select this to allow User to repeat courses completed as "In Progress"

- **If checked:** Kiosk will display "In Progress" course with a Play button to repeat course
- **If unchecked:** "In Progress" course will display Status but will **not** have a Play button

Playlists

Select Playlists that will be visible in Kiosk Mode.


- Select a **single** Playlist
 - User will not need to select an activity; Playlist will be ready
- Select **multiple** Playlists
 - User must choose which Playlist will play

Automatic Logout

Select to automatically exit a session after a period of inactivity. A Warning notification will appear prior to shutting down. Set Timeout in accordance with longest Company-Specific video.

- Defaults:
 - Timeout: 30 **minutes**
 - Warning: 30 **seconds**
- Minimums - Maximums:
 - Timeout: 1 - 999 **minute(s)**
 - Warning: 30 - 999 **seconds**

To keep the program active (and prevent a timeout) you must interact with the screen by answering questions and advancing to the next course.



Courses

Select to make all training activities (Courses, Tests, Evaluations) available in Kiosk Mode.

- Select All Courses
 - User must choose which activities will play